

Migrate 'Add comment'

The [Add comment post function of JWT DC](#) is also available for [JWT Cloud](#), with minor differences in terms of parameters and options.

The table below shows the detailed mapping between JWT DC and JWT Cloud.

Migration steps

- 1

Add the [Add comment post function](#).
- 2

Reconfigure the post function with the help of the following list, providing the necessary basics.

Migration details

JWT DC parameter	 JWT DC parameter options	 JWT Cloud parameter options	Notes
		Target issue: Current issue	Only available in JWT Cloud. Please use the default value Current issue .
Comment text	Add comment manually (parser expression)	- General parsing mode - Insert parser expression replacing JWT DC field codes with JWT Cloud field codes according to Migrate field codes	The list of available field codes differs between JWT DC and JWT Cloud.
	Copy field value from current issue	- This option is handled as a parser expression in JWT Cloud - General parsing mode - Insert JWT Cloud field code of the respective field according to Migrate field codes	The list of available field codes differs between JWT DC and JWT Cloud.
Comment visibility	Unrestricted (all users)	Unrestricted (all users)	
	Restricted to project role	Restricted to project role	The configured comment author must be a member of the configured role (see Add comment).
	Restricted to group	Restricted to group	The configured comment author must be a member of the configured group (see Add comment).
	Customer facing comment for Jira Service Management projects		Not available in JWT Cloud.

	Internal comment for Jira Service Management projects		Not available in JWT Cloud.
Additional Options	Send email notification		Not available in JWT Cloud.
Conditional execution		• Logical parsing mode • Parser expression according to Migrate JWT parser expressions	
Run as	A drop down menu where you can select a field (all available Fields are listed) The default is Current user	The options are equivalent to the ones in JWT DC but split in two separate entries: • Selected user , where you can pick a specific user • User in field, where all User fields (e.g. Assignee or Project lead as well as all custom fields of the type User picker (single user) are listed The default is the same as in JWT DC: Current user	This parameter is called Comment author in JWT Cloud. Since only those fields can be selected which hold a user it may happen that the value from JWT DC cannot be mapped to the respective field in JWT Cloud.

If you still have questions, feel free to refer to our [support](#) team.